PyMata API

```
init (self, port id='/dev/ttyACM0')
    \overline{\mathsf{The}} constructor instantiates the entire interface. It starts the operational threads for the serial
     interface as well as for the command handler.
    @param port id: Communications port specifier (COM3, /dev/ttyACM0, etc)
analog mapping query(self)
    Send an analog mapping guery message via sysex. Client retrieves the results with a
     call to get analog mapping request results()
analog read(self, pin)
     Retrieve the last analog data value received for the specified pin.
     @param pin: Selected pin
    @return: The last value entered into the analog response table.
analog write(self, pin, value)
    Set the specified pin to the specified value.
     @param pin: Pin number
    @param value: Pin value
     @return: No return value
capability query(self)
    Send a Firmata capability query message via sysex. Client retrieves the results with a
    call to get capability guery results()
close(self)
     This method will close the transport (serial port) and exit
    @return: No return value, but sys.exit(0) is called.
digital read(self, pin)
     Retrieve the last digital data value received for the specified pin.
    NOTE: This command will return values for digital, pwm, etc, pin types
     @param pin: Selected pin
    @return: The last value entered into the digital response table.
digital write(self, pin, value)
    Set the specified pin to the specified value.
    @param pin: pin number
    @param value: pin value
    @return: No return value
```

disable analog reporting(self, pin)

Disables analog reporting for a single analog pin.

@param pin: Analog pin number. For example for AO, the number is O.

@return: No return value

disable digital reporting(self, pin)

Disables digital reporting. By turning reporting off for this pin, reporting

is disabled for all 8 bits in the "port" -

@param pin: Pin and all pins for this port

@return: No return value

enable analog reporting(self, pin)

Enables analog reporting. By turning reporting on for a single pin,

@param pin: Analog pin number. For example for AO, the number is O.

@return: No return value

enable digital reporting(self, pin)

Enables digital reporting. By turning reporting on for all 8 bits in the "port" -

this is part of Firmata's protocol specification.

@param pin: Pin and all pins for this port

@return: No return value

encoder config(self, pin a, pin b)

This command enables the rotary encoder (2 pin + ground) and will enable encoder reporting.

NOTE: This command is not currently part of standard arduino firmata, but is provided for legacy

support of CodeShield on an Arduino UNO.

@param pin_a: Encoder pin 1.
@param pin b: Encoder pin 2.

@return: No return value

extended_analog(self, pin, data)

This method will send an extended data analog output command to the selected pin

@param pin: 0 - 127

@param data: 0 - 0xfffff

get_analog_mapping_request_results(self)

Call this method after calling <u>analog_mapping_query()</u> to retrieve its results @return: raw data returned by firmata

get analog response table(self)

This method returns a list of lists representing the current pin mode and associated data values for all analog pins.

All configured pin types, both input and output will be listed. Output pin data will contain zero. @return: The last update of the digital response table

get capability query results(self)

Retrieve the data returned by a previous call to capability_query()
@return: Raw capability data returned by firmata

get digital response table(self)

This method returns a list of lists representing the current pin mode and associated data for all digital pins.

All pin types, both input and output will be listed. Output pin data will contain zero.

@return: The last update of the digital response table

get firmata firmware version(self)

Retrieve the firmware id information returned by a previous call to refresh_report_firmware() @return: Firmata firmware list [major, minor, file name] or None

get firmata version(self)

Retrieve the firmata version information returned by a previous call to referesh_report_version() @return: Firmata version list [major, minor] or None

get_pin_state_query_results(self)

This method returns the results of a previous call to pin_state_query() and then resets
the pin state query data to None

@return: Raw pin state query data

```
NOTE: THIS METHOD MUST BE CALLED BEFORE ANY 12C REQUEST IS MADE
    This method initializes Firmata for I2c operations.
    It allows setting of a read time delay amount, and to optionally track
    the pins as I2C in the appropriate response table.
    To track pins: Set the pin type to ANALOG or DIGITAL and provide the pin numbers.
    If using ANALOG, pin numbers use the analog number, for example A4: use 4.
    @param read delay time: an optional parameter, default is 0
    @param pin type: ANALOG or DIGITAL to select response table type to track pin numbers
    @param clk pin: pin number (see comment above).
    @param data pin: pin number (see comment above).
    @return: No Return Value
i2c get read data(self, address)
    This method retrieves the i2c read data as the result of an i2c read() command.
    @param address: i2c device address
    Oreturn: raw data read from device
i2c read(self, address, register, number of bytes, read type)
    This method requests the read of an i2c device. Results are retrieved by a call to
    i2c get read data()
    @param address: i2c device address
    @param register: register number (can be set to zero)
    @param number of bytes: number of bytes expected to be returned
    @param read type: I2C READ or I2C READ CONTINUOUSLY
i2c stop reading(self, address)
    This method stops an I2C READ CONTINUOUSLY operation for the i2c device address specified.
    @param address: address of i2c device
i2c write(self, address, *args)
```

i2c config(self, read delay time=0, pin type=None, clk pin=0, data pin=0)

```
Write data to an i2c device.
    @param address: i2c device address
    @param args: a variable number of bytes to be sent to the device
pin state query(self, pin)
    This method issues a pin state query command. Data returned is retrieved via
    a call to get pin state query results()
    @param pin: pin number
play tone(self, pin, tone command, frequency, duration)
    This method will call the Tone library for the selected pin.
    If the tone command is set to TONE TONE, then the specified tone will be played.
    Else, if the tone command is TONE NO TONE, then any currently playing tone will be disabled.
    It is intended for a future release of Arduino Firmata
    @param pin: Pin number
    @param tone command: Either TONE TONE, or TONE NO TONE
    @param frequency: Frequency of tone
    @param duration: Duration of tone in milliseconds
    @return: No return value
refresh report firmware(self)
    This method will query firmata to report firmware. Retrieve the report via a
    call to get firmata firmware version()
refresh report version(self)
    This method will guery firmata for the report version.
    Retrieve the report version via a call to get firmata version()
reset(self)
    This command sends a reset message to the Arduino. The response tables will be reinitialized
    @return: No return value.
servo config(self, pin, min pulse=544, max pulse=2400)
    Configure a pin as a servo pin. Set pulse min, max in ms.
    @param pin: Servo Pin.
    @param min pulse: Min pulse width in ms.
    @param max pulse: Max pulse width in ms.
    @return: No return value
```

set pin mode(self, pin, mode, pin type)

This method sets a pin to the desired pin mode for the pin_type.

It automatically enables data reporting.

NOTE: DO NOT CALL THIS METHOD FOR I2C. See i2c_config().

@param pin: Pin number (for analog use the analog number, for example A4: use 4)

@param mode: INPUT, OUTPUT, PWM, SERVO, ENCODER or TONE

@param pin type: ANALOG or DIGITAL

@return: No return value

set sampling interval(self, interval)

This method sends the desired sampling interval to Firmata.

Note: Standard Firmata will ignore any interval less than 10 milliseconds @param interval: Integer value for desired sampling interval in milliseconds

@return: No return value.